

A coverage criterion can be seen as a finite set of test requirements that a test suite should fulfill. There is usually more than one way to cover a test requirement, so a coverage criterion is not a unique description of a test suite. To make use of coverage in practice we need to measure it. This is done by instrumenting the source code with an instrument for every single test requirement, described by the coverage criterion. When test cases are run on the instrumented program the instrumentation keeps track of what has been executed, and so at the end of the execution

Coverage can be used in three ways: 1) Adequacy: Have I got enough tests? 2) Guidance: Where should I test more? 3) Automation: Generate test that satisfies a test requirement

Coverage is usually quantified as the percentage of test requirements satisfied. But what does that mean?



Coverage is dangerous

- Developers write test only to satisfy coverage
- 100% coverage can detect no faults: Coverage measures what is *executed*, not what is *checked*
- Coverage metrics tell you what code is not tested, but cannot accurately tell you what code is tested:
 - Low coverage means code is not well tested
 - But high coverage does not mean code is well tested

The use of coverage has some dangerous aspects, that might even reduce the quality of testing. If success is only quantified in a coverage metric, developers will get very efficient and writing test cases that satisfy the coverage goals, but not at finding bugs. Also, it is possible to cover the entire program without detecting a single bug - testing is more than just input generation (see Mutation testing lecture).



Despite it's downsides coverage has some useful sides: It is very efficient at telling you which parts of a program you haven't tested at all. Intuitively, testing everything a little bit should be better than testing some aspect thoroughly and neglecting the rest - unless you already know where the bugs are (which you don't in general).





An arrow from one criterion to another means that the former subsumes the latter. This means that if we test for CoC, we will automatically satisfy all other coverage criteria as well. Determining infeasibility is undecidable, so what can we do in practice if we can't find a test case for a particular test requirement? A simple solution is to use a best effort approach: If, after some time, we cannot find a test case for a test requirement, we simply turn to the next simpler version of the same predicate in the subsumption hierarchy.

> All-definitions: One DU path for each definition All-c-uses: One DU path for each definition-c-use pair All-p-uses: One DU path for each definition-p-use pair All-c-uses-some-p-uses: One DU path for each definition-p-use pair If there is no p-use, then one c-use All-p-uses-some-c-uses All-DU-pairs: One DU path for each def-use pair: = Allp-uses +all-c-uses, also known as All-Uses All-DU-paths: All DU paths